
Format CALL JOYST(key-unit,x-return,y-return[,...])

Description

See EXTENDED BASIC MANUAL page 108

Except for adding auto repeat there is no changes to JOYST
Some of JOYST runs from ROM.

Programs

The program on the right will		>100 CALL CLEAR
illustrate a use of JOYST		>110 CALL SPRITE(#1,33,5,96,1
subprogram. It creates two		28,#2,42,2,96,128)
sprites and then moves them		>120 CALL JOYST(1,X1,Y1,2,X2,
around according to the input		Y2)
from the joysticks.		>130 CALL MOTION(#1,-Y1,X1,#2
Two players with the same		-Y2,X2)
input speed and motion.		>140 GOTO 120

Options:

See JOYMOTION, JOYLOCATE, KEY or ONKEY making it much more
easy to use then normal XB routines as it combines several
commands into a single command to use, also much faster
response and more variables are used to control routines
for a user.